



# Software Change Log



Valid for the following models:

- Hybrid Fomatic MAXCX
- Hybrid Foamtic SAXCX

Upgrade path:

- Always upgrade to newest version - NEVER downgrade!

Log:		
PLC & Display Software version	Changes	Software Manual Date
11013	Reading from SD card improved	14.01.2020
11012	Communication improved. Bug in password corrected. "Pumptop" sensor changed to "outlet"	10.09.2019
11011	Bug in start program after error corrected.	14.05.2019
11010	Bug in Low level product detection corrected. In Version 11000 low level product will always show low level product global.	25.09.2018
11000	Empty can pause functions implemented Support for 32 areas Satellite wash program pressure up to 25 bar OLDER CAN NOT BE UPGRADED TO 11000	25.09.2018
10200	TCP Socket communiton implemented for communication with external PLC Timing error in washprogram 10 and up corrected 10121 CAN NOT BE UPGRADED TO 10200!	04.2018
10121	Flow detection error time adjustable. Interval increased to 0-30 seconds. 0 seconds means function disabled.	11.08.2017
10120	Flow detection error implemented. Release error corrected. Data logging improved. Minor bug fixex.	11.08.2017
10111	Datalog on SD card improved.	08.06.2017
10110	Waterhammer function improved. Error for too big wash programs. Minor bug fixes.	15.05.2017
10100	Empty can function implemented. Waterhammer reduction fully implemented. Password protection for Auto and Setup menu. Error handling improved.	28.04.2017
10000	Initial release	31.01.2017

Document no: 110005442 01/20